## Install ERDAS Imagine 9.x

- 0) Make sure your ERDAS hardware key is attached to the parallel or USB port.
- 1) Go to the Control Panel Add Remove Programs and remove previous versions of ERDAS Imagine and the Leica License Manager. Restart the computer.
- 2) Insert the ERDAS disk, select Install Products ERDAS Imagine 91. -Licensing Tools. Install the Licensing tools using the defaults. Reboot.
- Insert the ERDAS disk again, select Install Products ERDAS Imagine 91. -ERDAS Imaging 9.1
- 4) Accept the license agreement and use all default folders and settings.
- 5) Open the license manager: Start Leica Geosystems Licensing tools License Management. Specify that your System ID is from a Hardware key. Click on the Add button.

Leica Geosystems Geospatial Imaging License Manager	½         Image: Source Information
System Information System Information System ID: d1fb3ad2e643fb System ID Source: Hardware Key Locense Source(a) The list of sources below is used to identify source of licenses. Use the "Add" botton to batelo license source information. The "Moddy" botton can be used to change a existing item and the "Remove will remove an item from the list.  Hardware Key Driver  Methods Key Driver  Install Driver Install Driver	You have: <ul> <li>Node locked license</li> <li>C License server information</li> <li>If you wish to name a license server enter van domation below. If you wish to name a license server, where the above settings we node locked licenses.</li> <li>Floating license setup</li> <li>Enter the name of a license server, you may use the "Browse" button to select one. If the floating licenses are for this machine you may use the "Wanage local license server.</li> <li>Server N mer:</li> <li>NASA19</li> <li>Browse</li> <li>Local license server</li> <li>This computer is the license server named above as a license server. You can enter footing licenses and start/stop the local license server.</li> <li>You can enter footing licenses and start/stop the local license server.</li> <li>Manage local license server</li> <li>Manage local license server.</li> <li>Manage</li></ul>
OK Help	OK Cancel Help

6) The License Source Information screen will appear. Select License server information and type the name of your computer in the Server name box. (The name of the computer in the example is NASA19). You can find the name of your computer by right-clicking on My Computer and look under the Computer name tab (do not include the period after the computer name). Click on *Manage local license server*.



## If that did not work there is still a chance!

- I) Open the FlexLM Tools: Start Leica Geosystems Licensing tools FlexLM Tools. Select 'Configure using Services'
- II) Click on the Config Services tab

LMTOOLS by Macrov	ision Corp	pration http://	www.macrovis	ion.com	$\backslash$		_ 🗆 ×
File Edit Mode Hel	p						1
Service/License File	System Set	tings   Utilities   :	Start/Stop/Reread	d   Server Status	Server Diags	Config Services	Borrowing
Configure Service					(	<u> </u>	
Service	e Name	EBDAS		-		Savese	ervice
		1				Remove S	ervice
Dath to the largest	L	C:\Program File	as\Leica Geosuste	ms\Shared\Bin	Browse		
Path to the Imgro	i.exe hie	je. v rogram na	ss (Leica deosyste	ans condied (bin	Desure	1	
Path to the lice	ense file	06\ERDAS9\d	11fb3ad2e643fb_0	228200625.lgs	DIOMSE	l	
Path to the debug	g log file	C:\Program File	es\Leica Geosyste	ms\ERDAS.log	Browse	View Log	Close Log
Г	Start Server	at Power Up	🗖 Use S	Services			
,							

- Select ERDAS for the Service Name or type in ERDAS if it is not available
- Browse to the path for the lmgrd.exe file:
- C:\Program Files\Leica Geosystems\Shared\Bin\NTx86\lmgrd.exe
- Browse to the path for your license file
- Specify a path and a name for the .log file. You can store this file anywhere and name it anything you want.
- Save service!

III) Click on the Start/Stop/Reread tab

LMTOOLS by Macrovision Corporation http://www.macrovision.com					
File Edit Mode Help					
Service/License File System Settings Utilities	Start/Stop/Reread Server Status Server Diags Config Services Bo	rrowing			
Flexi APU	m license Services installed on this computer	D.4 Tx1			
		1 st			
Start Server	Stop Server ReRead License File				
Advanced settings >>	Force Server Shutdown NOTE: This box must be checked to shut down a license server when licenses are borrowed.				
Using License File: C:\lab\ERDAS_2006\ERD	AS9\d1/b3ad2e643/b_0228200625.lgs				

Click on Stop Server (wait 30 seconds)

Click ReRead License File (wait 30 seconds). You may get the message that ReRead failed – this is normal.

Click Start Server